Enabling Access to the VMware vCenter Server Appliance (vCSA) Postgres Database

Contents	
Introduction to Enabling Access to the vCSA Postgres Database	1
Background	1
How to Enable Remote Access to the PostgreSQL Server and Collect Raw Data for Input to SAS IT Resource Management	. 1
Enabling Remote Access to the PostgreSQL Server	1
Collecting Raw Data for Input to SAS IT Resource Management	5

Introduction to Enabling Access to the vCSA Postgres Database

Background

SAS[®] IT Resource Management provides access to external vCenter databases through the SAS/ACCESS[®] to Oracle and SAS/ACCESS[®] to Microsoft SQL Server engines. These engines access the vCenter database in Read-Only mode and copy the tables and views that are needed by SAS IT Resource Management. Customers typically configure SAS IT Resource Management to access their operational vCenter external databases directly though some create mirrored copies of the vCenter database.

Note: Even for very large vCenter databases, SAS Read-Only access can copy the necessary tables in only few minutes.

Starting with vSphere 5.0U1, vCSA provides an option to use vPostgres (a VMware-flavored PostgreSQL) as its embedded database implemented as a closed system. For that reason, VMware publishes no guidance on how the vCenter Postgres database can be accessed directly or mirrored. In exploring the vCSA embedded PostgreSQL database however, the SAS IT Resource Management team discovered a method that, though not sanctioned by VMware, enables the adapter to connect to the vCSA vPostgres server.

How to Enable Remote Access to the PostgreSQL Server and Collect Raw Data for Input to SAS IT Resource Management

Enabling Remote Access to the PostgreSQL Server

To connect to the database remotely, perform the following steps, each of which is explained in more detail later in the document:

- 1. Modify the Postgres configuration to allow remote access.
- 2. Modify VMware's firewall to allow incoming Postgres connections.
- 3. Create the read-only Postgres user.

4. Check the database connection.

CAUTION:

These procedures are not supported by VMware.

However, the instructions were successfully tested using VMware 6.5 and 6.0. They also work using VCSA 5.5.

Modify the Postgres Configuration to Allow Remote Access

1. To enable your IP address to connect to the PostgreSQL server, enter this command:

vim /storage/db/vpostgres/pg_hba.conf

Then, add the following code to the bottom of that file: host all 1.2.3.4/24 md5

In this code, replace *1.2.3.4/24* with the actual IP address or range of addresses (for example, *192.168.1.0/24*). Alternatively, replace *1.2.3.4/24* with the server instance or ITRM server from which you want to access the database and run the SAS IT Resource Management adapter.

2. To ensure that the listen_addresses directive is properly configured, enter this command:

vim /storage/db/vpostgres/postgresql.conf

Note: If this directive is not present, then add the following code to the file: listen_addresses = '*'

3. To restart Postgres to apply changes, enter this command:

/etc/init.d/vmware-vpostgres restart

If the Postgres service does not restart properly, you can access the database connection errors by using the PGAdmin tool. For information about possible error messages, navigate to "Connection errors" at this location: https://www.pgadmin.org/docs/pgadmin3/1.22/connect-error.html.

```
To start (not restart) Postgres services, use following commands:
/opt/vmware/vpostgres/9.4/bin
sudo -u vpostgres ./pg_ctl -D /storage/db/vpostgres status
sudo -u vpostgres ./pg_ctl -D /storage/db/vpostgres stop -m fast
sudo -u vpostgres ./pg_ctl -D /storage/db/vpostgres start
```

Modify VMware's Firewall to Allow Incoming Postgres Connections

4. Enter this command:

```
vim /etc/vmware/appliance/firewall/vmware-vpostgres
```

Then make sure that this file contains the following code:

```
{
        "firewall": {
          "enable": true,
          "rules": [
            {
               "direction": "inbound",
              "protocol": "tcp",
              "porttype": "dst",
               "port": "5432",
              "portoffset": 0
            }
          ]
        },
        "internal-ports": {
          "rules": [
            {
               "name": "server_port",
               "port": 5432
            }
          ]
        }
      }
```

5. To reload the firewall, enter this command:

/usr/lib/applmgmt/networking/bin/firewall-reload

Create the Read-Only Postgres User

- 6. Log on to Postgres as the superuser account.
 - For the 6.0 database version, enter this command: /opt/vmware/vpostgres/9.3/bin/psql VCDB -U postgres
 - For the 6.5 database version, enter this command: /opt/vmware/vpostgres/9.4/bin/psql VCDB -U postgres
- 7. Create the role and grant the minimum necessary privileges by using the following SQL statements:

```
create role "vcenterVA_RO1" login password 'my_password';
GRANT CONNECT ON DATABASE "VCDB" TO "vcenterVA_RO1";
GRANT USAGE ON SCHEMA vc TO "vcenterVA_RO1";
GRANT SELECT ON ALL TABLES IN SCHEMA vc TO "vcenterVA_RO1";
```

8. As an alternative to the previous step, you can use the randomly generated password for your database user. To do so, navigate to /etc/vmware-vpx/vcdb.properties.

In this file, you can find the database user name vc and its password.

1	Example Snowing the User Name and Passwo	ra
	🔄 vcdb - Notepad 🗖 🗖	x
	File Edit Format View Help	
	<pre>driver = org.postgresql.Driver dbtype = PostgreSQL url = jdbc:postgresql://localhost:5432/VCDB username = vc password = pMJLoEPkB+F@Xlf4 password.encrypted = false</pre>	
		\sim
	< >	·

. .

Check the database connection.

After the previous steps are completed successfully, use the PGAdmin tool to check the database connection. To do so, perform the following steps:

- 9. Open PGAdmin and register the new server to establish a new connection to the database.
- 10. Specify values in the **Name** and **Host** fields. (Enter the user name and password that you used when creating the Postgres user in the previous list of steps.)
- 11. Deselect the **Store Password** check box.

📗 New Server R	egistration 🔀
Properties SSL	SSH Tunnel Advanced
Name .	postgres
Host	server.host.com
Port	5432
Service	
Maintenance DB	postgres
Username	vcenterVA_RO1
Password	J
Store password	
Colour	
Group	Servers
Help	<u>QK</u> <u>Cancel</u>

Register the New Server

Note: Attempting to connect from an external machine or an IP address cannot work without modification to postgresql.conf and pg_hba.conf. For information about making the required modifications, see the "Modify VMware's Firewall to Allow Incoming Postgres Connections" section. For information about possible error messages, navigate to "Connection errors" at this location: https://www.pgadmin.org/docs/pgadmin3/1.22/connect-error.html.

Collecting Raw Data for Input to SAS IT Resource Management

Note: You can access the vCenter Server Appliance Postgres database for use by SAS IT Resource Management in the same way that it accesses these vCenter external databases. For more information, see <u>VMware vCenter - Accessing Data</u>.

To configure access to VMware raw data in PostgreSQL Server database, perform the following steps: you must obtain information about the database. Then, you can configure ODBC on the SAS server and create the SAS library for the VMware raw data.

- 1. Configure ODBC on the SAS server.
- 2. Create the VMware Rawdata SAS Library.
- 3. Create a New External Database Server.
- 4. Specify a New Authentication Domain.

Configure ODBC on the SAS Server

1. Navigate to the **Drivers** tab of the ODBC Data Source Administrator. Verify that the PostgreSQL Server ODBC driver, PostgreSQL ANSI(x64), is available.

List of ODBC Installed Drivers

ODBC Data Source Adminis	trator	
User DSN System DSN File [OSN Drivers Tra	cing Connection Pooling About
ODBC Drivers that are installed	on your system:	
Name	Version	Company
Backup Exec Catalog Driver	Not marked	Not marked
NB SQL Anywhere	Not marked	Not marked
PostgreSQL ANSI(x64)	9.03.04.00	PostgreSQL Global Development G
PostgreSQL Unicode(x64)	9.03.04.00	PostgreSQL Global Development G
SAS ACCESS to Greenplum	7.10.04.166	SAS Institute Inc.
SAS ACCESS to SQL Server	7.10.04.197	SAS Institute Inc.
SQL Server	6.01.7601.17514	Microsoft Corporation
•		► I
An ODBC driver all ODBC data source program.	ows ODBC-enabled s. To install new dri	programs to get information from vers, use the driver's setup
0	K Cance	el <u>Apply</u> Help

2. Configure the data source.

a) On the **System DSN** tab, click **Add** to open the **Create new Data Source** window. Select **PostgreSQL Server**.

-	Select a driver for which you want to set up a da	ta source.
T	Name	Version
TOTTE	Microsoft Access Driver (*.mdb, *.accdb)	15.00.4543.10
	Microsoft Access Text Driver (*.bt, *.csv)	15.00.4543.10
	Microsoft Excel Driver (* xls, * xlsx, * xlsm, * xlst) 15.00.4543.10
	MySQL ODBC 5.1 Driver	5.01.06.00
	PostgreSQL ANSI(x64)	9.01.01.00
	PostgreSQL Unicode(x64)	9.01.01.00
	SQL Server	6.01.7601.175
	•	,

Note: The Unicode version of the driver does not work with the SAS IT Resource Management adapter.

- b) Click **Finish** to create the new data source. The setup screen for the new data source appears.
- c) As shown, below, enter the appropriate information in the following fields:
 - Database
 - Server
 - User Name
 - Password
- d) Click **Test** to verify your entries. Correct any entries that are incorrect.

When the "Connection successful" message appears in the information box, proceed to create the VMware raw data SAS library.

Create the VMware Rawdata SAS Library

To create the VMware raw data library, you must first create an ODBC library.

3. Log on as the unrestricted user to SAS Management Console connected to your SAS server. Invoke the **New Library Wizard** to create a new ODBC Library.

New Library Wizard



- 4. Provide the following information. (Click Next to navigate through the wizard.)
 - Enter a name for the database server (for example, *VMware*).
 - Enter the library name as *VMware*.
 - Select the SAS Application server.
 - Enter *vmware* in the **libref** field.
- 5. Click **Advanced Options**. Click **Other Options** to add any database-specific options. Then, click **OK**.
- 6. On the next screen, click **New** to create a new database server.

Create a New External Database Server

7. On the **New Server Wizard** page, enter a name for the database server (for example, *Vmware*).

New Server Wizard

New Server Wiz	ard						×
New Server & Specify the name	Wizard ne and description	for the new ODBC Ser	ver.				000
Na <u>m</u> e:	VMWARE						
Descri <u>p</u> tion:							*
	,						_
			< <u>B</u> ack	<u>N</u> ext >	Einish	Cancel	Help

8. On the next page, enter the server properties as shown in the following display:

New Server Wizard						×
New Server Wizard Enter the following server	properties.					
••						
Major version number:						_
Minor version number:	0					
Data Source Type:	ODBC - Other Database					•
Software version:						
Vendor:	[
Associated Machine:	server.host.com				-	Ne <u>w</u>
		< Back	Next >	Finish	Cancel	Help
			<u></u>			

Server Properties Page of the New Server Wizard

9. On the next page, specify the ODBC data source. (This name should be one that you specified when configuring the ODBC library.)

New Server Wizard					×
New Server Wizard Enter the connection propertie	es.				
ODBC Data Source Informal	tion				
Specify either the ODBC	data source to which you wa	ant to connect or the ODB	C connection string.		
Oatasrc:	VMWARE				
C Connection String:					
Authentication Information					
Enter the authentication	information needed to conne	ect to this server			
Authentication type:	User/Password				-
Authentication domain:	DefaultAuth			•	Ne <u>w</u>
		< <u>B</u> ack <u>N</u> ext	> Enish	Cancel	Help

Connection Properties Page of the New Server Wizard

10. Click New to specify the name of the authentication domain. Click OK.

New Auth	entication Domain	
🛅 New Auti	nentication Domain	×
Name:	vmware	
Description:		
Cutbour	d only 🔲 Trusted only	
	OK Cancel <u>H</u>	elp

. . n

11. On the next page, review the settings that you entered. Click **Finish** to create the new Database Server.

Specify the Server and Connection Information

w Library Wiza cify the server an	rd d connection information.		0.0
Server Details			
Database Serve	er: vmware		New
Database Schgr	na Name:	 	
Connection Detail	s		
\underline{C} onnection:	Connection: vmware	×	New
Default Login:	(None)		

12. On the next page, review the settings and revise as necessary. Click **Finish** to create the new library.

Specify a New Authentication Domain

- 13. Select **User Manager** and choose the user for whom you want to add the new authentication domain.
 - **Note:** The new authentication domain can be added for a group, if needed.
- 14. Select the Account tab and click New to display the Edit Login Properties window.

As shown below, enter the **User ID** and **Password** credentials along with the **Authentication Domain**.

a shall character at Dislam (Accourt	te Laurence L		
neral Groups and Roles Account	us Authorization		
ogins defined for sinsuo			
Authentication Domain	User ID	Password	New
efaultAuth	row\ssssss	*****	Edit
mware	vcenterVA_RO1	******	Euli
			Delete
Edit Login Properties			×
Edit Login Properties	_		×
Edit Login Properties	inter User IDs for Microsoft W	/indows in the format of	×
Edit Login Properties Enter Login information. E domain\userid. See help f	inter User IDs for Microsoft W or details.	/indows in the format of	×
Edit Login Properties Enter Login information. E domain\userid. See help fr	inter User IDs for Microsoft W or details.	/indows in the format of	×
Edit Login Properties Enter Login information. E domain\userid. See help fo User ID:	inter User IDs for Microsoft W or details. vcenterVA_RO1	/indows in the format of	×
Edit Login Properties Enter Login information. E domain\userid. See help fi User ID:	inter User IDs for Microsoft W or details. vcenterVA_RO1	/indows in the format of	
Edit Login Properties Enter Login information. E domain\userid. See help fr User ID: Password:	inter User IDs for Microsoft W or details. vcenterVA_RO1 ******	/indows in the format of	
Edit Login Properties Enter Login information. E domain\userid. See help fr User ID: Password: Confirm Password:	inter User IDs for Microsoft W or details. vcenterVA_RO1 ******** ****	/indows in the format of	
Edit Login Properties Enter Login information. E domain\userid. See help fr User ID: Password: Confirm Password:	inter User IDs for Microsoft W or details. vcenterVA_RO1 ******** ****	/indows in the format of	X
Edit Login Properties Enter Login information. E domain\userid. See help fr User ID: Password: Confirm Password: Authentication Domain:	inter User IDs for Microsoft W or details. vcenterVA_RO1 ******** ********	Vindows in the format of	
Edit Login Properties Enter Login information. E domain\userid. See help fr User ID: Password: Confirm Password: Authentication Domain:	inter User IDs for Microsoft W or details. vcenterVA_RO1 ******** ******** vmware	Vindows in the format of	
Edit Login Properties Enter Login information. E domain\userid. See help fo User ID: Password: Confirm Password: Authentication Domain:	inter User IDs for Microsoft W or details. vcenterVA_RO1 ******** ******** vmware	/indows in the format of	

15. Click **OK** to complete the specification of the authentication domain. The library VMware is now available. It can be used to specify the **Rawdata** field when you set up a VMware IT Data Mart.